

Installing APP

Steps to Install “DUALCAM2” the camera App (The bash-terminal code provided might not exactly work, but ChatGPT should provide you with one that looks similar)

- 1) Installed Anaconda (this is the version I have)

```
(base) lucactive@Lucas-MacBook-Air-10 ~ % conda --version  
  
conda 24.9.2
```

- 2) Install VSCode, maybe other coding platforms work as well

- 3) Install Python (this is the version I have)

```
[(base) lucactive@Lucas-MacBook-Air-10 ~ % python --version  
Python 3.12.7
```

- 4) Unzip the zipped folder and then install the specific environment called “environment.yml”. ChatGPT can be very useful here, especially to give exact bash terminals, but below is a generic one that works if the environment is saved in the downloads file:


```
“cd ~/Downloads  
conda env create -f environment.yml”
```

- 5) Activate the environment using terminal bash code, a generic one is below:

```
“cd ~/Downloads  
conda env create -f environment.yml”
```

- 6) Once all these platforms and environments have been installed, run the bash terminal code to open the camera app. Since I have it stored in my downloads folder, the bash terminal code is as follows: “python3 ~/Downloads/DUALCAM2.py”

How to use the APP



- 1) The first UI (user interface) interaction is where you can save the file name
- 2) The last button called "Restart App" restarts the app completely, it is equivalent to exiting out of the terminal and restarting the app from scratch. If the UI stops responding, going through the terminal is the best way
- 3) The app will not show the live view of the cameras until the button "Refresh Camera View" is pressed
- 4) The app won't allow the same camera to be selected twice, and you can press the "Refresh Camera View" button as needed to update the views when the cameras in the "Camera Positions" are switched.
- 5) If you add a new camera after the app is opened, hit the "Restart App" button so that the camera appears as well
- 6) This app will take the first set of pictures immediately after the "Start Taking Pictures" button is pressed, and it will save the photos from both cameras into a folder called whatever appears under "Folder name", and it will appear in your downloads file. It will take 20 pictures from each camera, 5 seconds apart. The photos from the different cameras are labelled differently to distinguish them.